


Consignes

User Guide V1.00




Buddy[®]
The Emotional Robot



1 - SUMAMRY

1 - SUMAMRY	2
2 - ABOUT	4
2.1 - PREREQUISITES	5
2.2 - FUNCTIONING	5
3 - FEATURES	6
3.1 - HOME	7
3.2 - ADD AN INSTRUCTION	8
3.3 - CREATE A CATEGORY	10
3.4 - START LISTENING	10
3.5 - SETTINGS	11
4 - CONTACT US	13
4.1 - CONTACT INFORMATIONS	14






2 - ABOUT

2.1 - PREREQUISITES

The Consigne app serves two purposes: creating personalized pictograms and aiding in the understanding of complex vocabulary words and instructions.

2.2 - FUNCTIONING


When the application launches, a gallery of commands is displayed by default. You can create your own content and adjust the application settings to customize your experience. You can then click on a command to view it, or start listening mode so that Buddy recognizes voice commands and automatically displays the command details (image, video, or definition).





3 - FEATURES

3.1 - HOME



When the application launches, your gallery of instructions or pictograms is displayed. A default category consists of school-related instructions.


- 1 To play a command, click on the command of your choice.
- 2 To create a command, click the "Add command" button or the "+" button in the top right corner.
- 3 To trigger listening on Buddy, click the "ear" icon.
- 4 To access the app settings, click the "gear" icon.
- 5 You can mark commands as "favorites" by clicking the "star" icon on the command. To remove a command from the "favorites" category, uncheck the star.
- 6 To edit a command, click the "edit" button on the command.

3.2 - ADD AN INSTRUCTION


The screenshot shows a mobile application interface for creating an instruction. The title bar is teal with a checkmark icon on the left, a back arrow, the title 'CRÉER UNE CONSIGNE', a settings gear icon, and a close 'X' icon. The form has four main sections: 1. 'Nom de la consigne' (Instruction name) with a text input field containing the placeholder 'Nom'. 2. 'Catégorie' (Category) with a dropdown menu showing 'Sélectionner une catégorie' and a '+' button to add new categories. 3. 'Image à afficher' (Image to display) featuring a large preview area with a cartoon character's face and the text 'Cliquez pour sélectionner une image'. To the right of the preview are four circular icons: a red trash can, a magnifying glass, a camera, and a video camera. 4. 'Définition' (Definition) with a text input field. At the bottom is a teal 'Enregistrer' (Save) button with a checkmark icon.

To create an instruction:

- Enter the name of your instruction in the “instruction name” field
- Select a category
- If you haven’t created a category yet, click the “+” button to create one
- Choose either to take a photo or video using Buddy’s camera, or select an icon by clicking the “search” button (magnifying glass)



Taking a photo



Select an icon from the icon library.


- Optional: You can write a definition or explanatory text for your instruction. If you click in the "definition" field, a keyboard appears.
- Click "Save" once all the fields are filled in.

3.3 - CREATE A CATEGORY




Enter the name of your category in the “new category name” field, then click “confirm”.

3.4 - START LISTENING



- Tap the «ear» icon in the top-right corner of your Buddy's screen.
- When listening mode is active, the icon turns blue, and wave patterns appear as a transparent overlay on your robot's face.
- In listening mode, Buddy can recognize the names of the commands configured in your gallery. If he recognizes a command, he will execute it instantly.


3.5 - SETTINGS




- Enable/disable continuous listening mode: If continuous listening mode is enabled, Buddy listens constantly and attempts to recognize voice commands while the app is running.
- Enable/disable definition playback: If playback is enabled, Buddy reads the definition of the selected or detected command aloud.
- Enable/disable definition display: If definition display is enabled, Buddy shows the text definition of the selected command.
- Enable/disable video display: If video display is enabled, the video recorded when the command was created plays on Buddy whenever the command is displayed.
- Button size: You can adjust the size of your command buttons to customize how your commands appear in your gallery.



Example of displaying an instruction without displaying the definition.



Example of an instruction displayed with its definition.



4 - CONTACT US



4.1 - CONTACT INFORMATIONS

If you wish to contact us for further information, please refer to the following addresses.

Support
service-client@buddytherobot.com

Common informations
info@bluefrogrobotics.com